



HPC, Inc.
3999 N. 25th Avenue
Schiller Park, IL 60176 USA
www.hpcworld.com

Installation Instructions CodeSource® Pocket for Pocket PC

System Requirements:

PC running Windows98, WindowsME, Windows2000, or WindowsXP (Home or Professional) and Microsoft ActiveSync already installed on the PC.

Handheld device running Pocket PC, Pocket PC 2002, or Pocket PC 2003 (Windows® Mobile) operating systems. This handheld must have at least 20 MB of free internal memory. You may use the Memory management application, accessed from your unit's Settings menu to view and adjust memory allocations.

Installing the CodeSource® Pocket program files:

1. Place your Pocket PC device in its cradle and/or attach it to your desktop PC with the appropriate cable. Be certain that Microsoft ActiveSync is running and connected to the handheld unit.
2. Place the CodeSource® Pocket CD in your computer. If the installation program does not start, double click **My Computer**, double click your CD drive and double click **Setup**, an Internet document.
3. Click either **Install CodeSource for Pocket PC Program** or **Install CodeSource Pocket PC Program on Windows Mobile 5**, depending on the version of Pocket PC you have. You will be prompted to Open or Save the file. Click **Open**. You may be warned about accepting files from an unknown source. Click Open or Accept on this window.
4. Click **Next**. The HPC End User License Agreement will appear. Click **I accept** to indicate your approval of the Agreement. If you do not approve, CodeSource® Pocket will not be installed.
5. Click **Next**. CodeSource® Pocket files will be extracted from the CD-ROM and prepared for installation to your Pocket PC device.
6. ActiveSync will then ask you to check your PC for additional steps for installation. On your Pocket PC click **Yes to all** to replace .dll files.
7. Click **Finish** to exit the installation on your computer.
8. After the initial installation is complete, the data files must be installed. Click **Install CodeSource for Pocket PC Data Files** to either **Internal Memory** or a **Storage Card**.
9. Click **2006 Update Install** sections 1 through 5. You will be prompted to Open or Save each section. Click **Open**. Follow the on-screen instructions. You may have to click Tools and Add/Remove Programs in ActiveSync to start the download.
10. After all sections are successfully installed, disconnect the Pocket PC from the PC. There will be an HPC CodeSource® icon on the Programs screen. Tap the icon to start the CodeSource® Pocket program.

Technical Support:

If you need help with any aspect of CodeSource® Pocket, you should first go to the on-screen help in the program. HPCSoft™ has provided extensive help information to easily guide you through the program. If you are unable to resolve a problem, contact HPC at:

Tel: 847.671.6280
800.323.3295
Monday - Friday, 8:00am - 4:30pm (CST)
Fax: 847.671.6343
Email: software@hpcworld.com

If you are having any difficulties with Pocket PC Operating System, refer to your Pocket PC User Manual or contact your Pocket PC manufacturer.

HPCSoft™ technical support is free of charge to registered users. A registration card is supplied with this product. Please have your serial number handy when contacting HPCSoft™. When contacting us by phone, it is most helpful to be calling from the computer where you need support. This way we can work with you to solve the problem or demonstrate a particular function of the software.